


EIGRP-DHCP-DNS-WEB Uygulaması

www.andabilgi.com

www.arslanacar.com



Merkez

```
Router>en
Router#conf

Router(config)#hostname Merkez

Merkez(config)#enable password sifre

Merkez(config)#line con 0
Merkez(config-line)#password sifre
Merkez(config-line)#login

Merkez(config-line)#line vty 0 15
Merkez(config-line)#login
Merkez(config-line)#enable password sifre

Merkez(config)#service password-encryption

Merkez(config)#banner motd !
Merkez Router
!

Merkez(config)#no ip domain-lookup

Merkez(config)#int s0/0/0
Merkez(config-if)#ip address 11.0.1.1 255.255.255.252
Merkez(config-if)#no shut
Merkez(config-if)#clock rate 64000
```

```
Merkez(config)#int fa0/0
Merkez(config-if)#ip address 10.1.1.1 255.255.255.0
Merkez(config-if)#no shut
```

```
Merkez(config)#int fa0/1
Merkez(config-if)#ip address 10.1.2.1 255.255.255.0
Merkez(config-if)#no shut
```

```
Merkez(config)#router eigrp 13
Merkez(config-router)#network 10.1.1.0 0.0.0.255
Merkez(config-router)#network 10.1.2.0 0.0.0.255
Merkez(config-router)#network 11.0.1.0 0.0.0.3
Merkez(config-router)#no auto-summary
```

```
Merkez(config)#int fa0/1
Merkez(config-if)#ip helper-address 10.1.1.254
```

Ankara

```
Router>en
Router#conf
```

```
Router(config)#hostname Ankara
```

```
Ankara(config)#enable password sifre
```

```
Ankara(config)#line con 0
Ankara(config-line)#password sifre
Ankara(config-line)#login
```

```
Ankara(config-line)#line vty 0 15
Ankara(config-line)#login
Ankara(config-line)#enable password sifre
```

```
Ankara(config)#service password-encryption
```

```
Ankara(config)#banner motd !
Ankara Router
!
```

```
Ankara(config)#no ip domain-lookup
```

```
Ankara(config)#int s0/0/0
Ankara(config-if)#ip address 11.0.1.2 255.255.255.252
Ankara(config-if)#no shut
```

```
Ankara(config-if)#int fa0/0
Ankara(config-if)#ip address 10.2.1.1 255.255.255.0
Ankara(config-if)#no shut
```

```
Ankara(config-if)#int fa0/1
```

```
Ankara(config-if)#ip address 10.2.2.1 255.255.255.0
Ankara(config-if)#no shut
Ankara(config)#router eigrp 13
Ankara(config-router)#network 11.0.1.0 0.0.0.3
Ankara(config-router)#network 10.2.1.0 0.0.0.255
Ankara(config-router)#network 10.2.2.0 0.0.0.255
Ankara(config-router)#no auto-summary
```

```
Ankara(config)#int fa0/0
Ankara(config-if)#ip helper-address 10.1.1.254
Ankara(config-if)#int fa0/1
Ankara(config-if)#ip helper-address 10.1.1.254
```