


ROUTER TEMEL KONFIGÜRASYONU

www.andabilgi.com

www.arslanacar.com



Router R1

```
Router#erase startup-config
```

```
Router#reload
```

```
Router(config)#hostname R1
```

```
R1(config)#no ip domain-lookup
```

```
R1(config)#enable password cisco
```

```
R1(config)#service password-encryption
```

```
R1(config)#banner motd !
```

```
R1 Router
```

```
!
```

```
R1(config)#line con 0
```

```
R1(config-line)#password cisco
```

```
R1(config-line)#login
```

```
R1(config)#line vty 0 15
```

```
R1(config-line)#login
```

```
R1(config-line)#enable password cisco
```

```
R1(config)#int s0/0/0
```

```
R1(config-if)#ip address 192.168.2.1 255.255.255.0
```

```
R1(config-if)#clock rate 64000
```

```
R1(config-if)#no shut
```

```
R1(config)#int fa0/0
```

```
R1(config-if)#ip address 192.168.1.1 255.255.255.0
```

```
R1(config-if)#no shut
```

```
R1(config)#ip route 192.168.3.0 255.255.255.0 s0/0/0
```

```
R1(config-if)#do wr
```

```
R1#show ip route
```

```
R1#sh ip interface brief
```

Router R2

Router#erase startup-config

Router#reload

Router(config)#hostname R2

R2(config)#no ip domain-lookup

R2(config)#enable password cisco

R2(config)#service password-encryption

R2(config)#banner motd !

R2 Router

!

R2(config)#line con 0

R2(config-line)#password cisco

R2(config-line)#login

R2(config)#line vty 0 15

R2(config-line)#login

R2(config-line)#enable password cisco

R2(config)#int s0/0/0

R2(config-if)#ip address 192.168.2.2 255.255.255.0

R2(config-if)#no shut

R2(config)#int fa0/0

R2(config-if)#ip address 192.168.3.1 255.255.255.0

R2(config-if)#no shut

R2(config)#ip route 192.168.1.0 255.255.255.0 s0/0/0

R2(config-if)#do wr

R2#show ip route

R2#sh ip interface brief